

AMPMK9 Certificate Patch 2020

Issue

If the machine is currently installed with PMK9.03 or prior, upgrading to the latest certificates using AMPMK Service Pack 3 may encounter issues, so it is recommended the user installing PMK9.04 before installing AMPMK Service Pack 3. However, installing PMK9.04 might cause inconvenience as the SSD will be re-imaged.

AMPMK9 Certificate Patch 2020 is designed for customer who do not want to re-image SSD on machine but need the new ANCA Group certificate to install new application software. It is a small-sized patch just to update to the latest 2020 certificate on machine. This patch will only update certificates but not bringing the platform to the very latest, and can be installed on any PMK9 products.

Product

Product	Download Link
AMPMK9-CertificatePatch2020.zip	https://motion.anca.com/Anca.Motion/media/Software-Downloads/AMPMK9-CertificatePatch2020.zip

Applications

Product	Part Number	Correct Image Version
PMK V9.01	963-0-01-0049	SW646-0-01-5000
PMK V9.02	963-0-02-0049	9.2.39239
PMK V9.03	963-0-03-0049	9.3.46557
PMK V9.03.1	963-1-03-0049	9.3.46557
PMK V9.03.2	963-2-03-0049	9.3.46557
PMK V9.04	963-0-04-0049	9.4.67198

Note: Please refer to Image Version Checking section for more details.

Actions

- The preferred solution is to follow the recommendation as described in “D-000108_ANCA Motion CNC PMK Usage - Approved Usage List OEM Customers.PDF” document to perform a proper update by installing PMK 9.04 first followed by either ANCA Motion Service Pack 3 or AMPMK9 Certificate Patch 2020.
- AMPMK9 Certificate Patch 2020 is another option for a convenient path to just add certificate without changing the PMK version and re-image SSD on machine.

Appendix

Image Version Checking

1. Open a command prompt
Open Windows Explorer and type "C:\Windows\System32\cmd.exe".




Figure 1 – Command Prompt

2. At the command line type
"reg query HKLM\SOFTWARE\ANCAMotion /v EmbeddedImageVersion"




Figure 2 - Image Version Registry

Setup to Install AMPMK9 Certificate Patch 2020

1. First, right click the AMPMK9-CertificatePatch2020.zip, select "7-Zip", and then select "Extract Here", as shown in Figure 3.




Figure 3 - Extract file

2. Extract “AMPMK9-CertificatePatch2020.zip” to target CNC or storage device, as shown in Figure 4.




Figure 4 - Installation Files

3. Double click “Setup.exe” as shown in Figure 5. And then a “Setup Wizard” will be shown as in Figure 6.




Figure 5 - Setup



Figure 6 - Setup Wizard

4. And then a “Dialog Box” is displayed as shown in Figure 7, click “Install” button to start. After the installation process is finished another “Dialog Box” is displayed as shown in Figure 8. Please click “Close” button to complete installation.




Figure 7 – Installation




Figure 8 - Installation finish



Product, Sales, and Service Enquiries

If you require additional assistance for installation, training, or other customer support issues, please contact the closest ANCA Motion Customer Service Office in your area for additional details.

ANCA Motion Pty. Ltd.

1 Bessemer Road
Bayswater North
VIC 3153
AUSTRALIA
Telephone: +61 3 9751 8900
Fax: +61 3 9751 8901
www.ancamotion.com/Contact-Us
Email: sales.au@ancamotion.com

ANCA Motion Taiwan

4F., No.63, Jingke Central Rd., Nantun Dist.,
Taichung City 40852,
TAIWAN
Telephone: +886 4 2359 0082
Fax: +886 4 2359 0067
www.ancamotion.com/Contact-Us
Email: sales.tw@ancamotion.com

ANCA Motion China

No. 102, Building F1
XEDA Emerging Industrial Park
Xiqing Economic-technological Development Area
Tianjin, P.R.China
Telephone: +86 22 5965 3760
Fax: +86 22 5965 3761
www.ancamotion.cn/Contact-Us
Email: sales.cn@ancamotion.com



END

AMPMK9 Certificate Patch 2020